

StarterToProcessVariableActionHandler

Previously known as the StartToProcessVariableActionHandler - renamed in TIM [Version 4.2](#)

Description

This [handler](#) adds a variable to the process. It also adds the user name of the instance starter as the value.

This variable and its values are shown in the PDF-report in the smartform area.

The default variable name is „Starter“. However, an arbitrary name may be entered into the mandatory field.

In order to assign the instance starter to a specific swimlane, the following handler may be used: [AssignStarterToSwimlaneHandler](#)

The following variables will be generated:

- starter / prefix value : UserName
- starter / prefix value + Expression (z.B. starterExpression) : user(Username)
- starter / prefix value + Firstname (z.B. starterFirstname) : First name
- starter / prefix value + Lastname (z.B. starterLastname) : Last name
- starter / prefix value + Email(z.B. starterEmail) : E-mail address
- starter / prefix value + Department(z.B. starterDepartment) : Department

For example: Standard:

```
starter:MHI
starterExpression:user(MHI)
starterFirstname:Markus
starterLastname:Hirscher
starterEmail:Markus.Hirscher@example.de
starterDepartment:HR
```

in the example under:

```
starteroptionalervariablenname:MHI
starteroptionalervariablennameExpression:user(MHI)
starteroptionalervariablennameFirstname:Markus
starteroptionalervariablennameLastname:Hirscher
starteroptionalervariablennameEmail:Markus.Hirscher@example.de
starteroptionalervariablennameDepartment:HR
```

or with start_ :

```
start_:MHI
start_Expression:user(MHI)
start_Firstname:Markus
start_Lastname:Hirscher
start_Email:Markus.Hirscher@example.de
start_Department:HR
```

Action Class

`com.dooris.bpm.actionhandler.StarterToProcessVariableActionHandler`

Event Type

any

Action Name

any


Mandatory Fields

Prefix - if empty the standard starter is used as a prefix

Parameter

not necessary

Example



From: <https://wiki.tim-solutions.de/> - **TIM Wiki** / [NEW TIM 6 Documentation](#)

Permanent link: <https://wiki.tim-solutions.de/doku.php?id=en:software:tim:actionhandler:startertoprocessvariableactionhandler>

Last update: **2021/07/01 09:52**

