

# StarterToProcessVariableActionHandler

Previously known as the StartToProcessVariableActionHandler - renamed in TIM [Version 4.2](#)

## Description

This [handler](#) adds a variable to the process. It also adds the user name of the instance starter as the value.

This variable and its values are shown in the PDF-report in the smartform area.

The default variable name is „Starter“. However, an arbitrary name may be entered into the mandatory field.

In order to assign the instance starter to a specific swimlane, the following handler may be used:  
[AssignStarterToSwimlaneHandler](#)

The following variables will be generated:

- starter / prefix value : UserName
- starter / prefix value + Expression (z.B. starterExpression) : user(Username)
- starter / prefix value + Firstname (z.B. starterFirstname) : First name
- starter / prefix value + Lastname (z.B. starterLastname) : Last name
- starter / prefix value + Email(z.B. starterEmail) : E-mail address
- starter / prefix value + Department(z.B. starterDepartment) : Department

For example: Standard:

starter:MHI  
starterExpression:user(MHI)  
starterFirstname:Markus  
starterLastname:Hirscher  
starterEmail:Markus.Hirscher@example.de  
starterDepartment:HR

in the example under:

starteroptionaler\_variablenname:MHI  
starteroptionaler\_variablennameExpression:user(MHI)  
starteroptionaler\_variablennameFirstname:Markus  
starteroptionaler\_variablennameLastname:Hirscher  
starteroptionaler\_variablennameEmail:Markus.Hirscher@example.de  
starteroptionaler\_variablennameDepartment:HR

or with start\_ :

start\_:MHI  
start(Expression):user(MHI)  
start\_Firstname:Markus  
start\_Lastname:Hirscher  
start\_Email:Markus.Hirscher@example.de  
start\_Department:HR

## Action Class

```
com.dooris.bpm.actionhandler.StarterToProcessVariableActionHandler
```

---

## Event Type

any

## Action Name

any

## Mandatory Fields

Prefix – if empty the standard starter is used as a prefix

## Parameter

not necessary

---

## Example

Symboleigenschaften - Aktivität

Symbol:

BPMN-Anleitung:

Modellierung:

Eingaben:

Ressourcen:

Aufgabe:

Ausgaben:

Attribute:

Letzte Simulation:

Sonstige:

Allgemein:

Verknüpfungen:

Benutzerdefinierte Daten:

Risiken:

Messgrößen:

RACI:

Automatisierung:

Enterprise:

Solldauer:

Aufgabenliste:

Aufgabenname	Rollenzuweisung

**Edit Event**

Ereignistyp: Node Leave

Aktionsname: StarterToProcessVariableActionHandler

Aktionsklasse: onhandler.StartToProcessVariableActionHandler

Mandatory Fields: optionaler\_variablenname

Parameter:

OK Abbrechen

Fields Parameter

OK Abbrechen Übernehmen Hilfe

From:  
<https://wiki.tim-solutions.de/> - TIM Wiki / [NEW TIM 6 Documentation](#)

Permanent link:  
<https://wiki.tim-solutions.de/doku.php?id=en:software:tim:actionhandler:startertoprocessvariableactionhandler&rev=1507534373>

Last update: 2021/07/01 09:54

