

StarterToProcessVariableActionHandler

Previously known as the StartToProcessVariableActionHandler - renamed in TIM [Version 4.2](#)

Description

This [handler](#) adds a variable to the process. It also adds the user name of the instance starter as the value.

This variable and its values are shown in the PDF-report in the smartform area.

The default variable name is „Starter“. However, an arbitrary name may be entered into the mandatory field.

In order to assign the instance starter to a specific swimlane, the following handler may be used:
[AssignStarterToSwimlaneHandler](#)

The following variables will be generated:

- starter / prefix value : UserName
- starter / prefix value + Expression (z.B. starterExpression) : user(Username)
- starter / prefix value + Firstname (z.B. starterFirstname) : First name
- starter / prefix value + Lastname (z.B. starterLastname) : Last name
- starter / prefix value + Email(z.B. starterEmail) : E-mail address
- starter / prefix value + Department(z.B. starterDepartment) : Department

For example: Standard:

starter:MHI
starterExpression:user(MHI)
starterFirstname:Markus
starterLastname:Hirscher
starterEmail:Markus.Hirscher@example.de
starterDepartment:HR

in the example under:

starteroptionaler_variablenname:MHI
starteroptionaler_variablennameExpression:user(MHI)
starteroptionaler_variablennameFirstname:Markus
starteroptionaler_variablennameLastname:Hirscher
starteroptionaler_variablennameEmail:Markus.Hirscher@example.de
starteroptionaler_variablennameDepartment:HR

or with start_ :

start_:MHI
start(Expression:user(MHI)
start_Firstname:Markus
start_Lastname:Hirscher
start_Email:Markus.Hirscher@example.de
start_Department:HR

Action Class

com.dooris.bpm.actionhandler.StartToProcessVariableActionHandler

Event Type

any

Action Name

any

Mandatory Fields

Prefix – if empty the standard starter is used as a prefix

Parameter

not necessary

Example

Symboleigenschaften - Aktivität

Symbol:

BPMN-Anleitung:

Modellierung:

Eingaben:

Ressourcen:

Aufgabe:

Ausgaben:

Attribute:

Letzte Simulation:

Sonstige:

Allgemein:

Verknüpfungen:

Benutzerdefinierte Daten:

Risiken:

Messgrößen:

RACI:

Automatisierung:

Enterprise:

Solldauer:

Aufgabenliste:

Aufgabenname	Rollenzuweisung
Edit Event	
Ergebnistyp:	Node Leave
Aktionsname:	StarterToProcessVariableActionHandler
Aktionsklasse:	onhandler.StartToProcessVariableActionHandler
Mandatory Fields:	optionaler_variablenname
Parameter:	

OK Abbrechen Übernehmen Hilfe

From:
<https://wiki.tim-solutions.de/> - TIM Wiki / [NEW TIM 6 Documentation](#)

Permanent link:
<https://wiki.tim-solutions.de/doku.php?id=en:software:tim:actionhandler:startertoprocessvariableactionhandler&rev=1453378742>

Last update: 2021/07/01 09:54

