

StarterToProcessVariableActionHandler

Previously known as the StartToProcessVariableActionHandler - renamed in TIM [Version 4.2](#)

Description

This [handler](#) adds a variable to the process. The variable is not visible in the smartform. It also adds the user name of the instance starter as the value.

This variable and its values are shown in the PDF-report in the smartform area.

The default variable name is „Starter“. However, an arbitrary name may be entered into the mandatory field.

In order to assign the instance starter to a specific swimlane, the following handler may be used:
[AssignStarterToSwimlaneHandler](#)

The following variables will be generated:

- starter / prefix value : UserName
- starter / prefix value + Expression (z.B. starterExpression) : user.Username
- starter / prefix value + Firstname (z.B. starterFirstname) : First name
- starter / prefix value + Lastname (z.B. starterLastname) : Last name
- starter / prefix value + Email(z.B. starterEmail) : E-mail address
- starter / prefix value + Department(z.B. starterDepartment) : Department

For example: Standard:

starter:MHI
starterExpression:user(MHI)
starterFirstname:Markus
starterLastname:Hirscher
starterEmail:Markus.Hirscher@example.de
starterDepartment:HR

in the example under:

starteroptionaler_variablename:MHI
starteroptionaler_variablenameExpression:user(MHI)
starteroptionaler_variablenameFirstname:Markus
starteroptionaler_variablenameLastname:Hirscher
starteroptionaler_variablenameEmail:Markus.Hirscher@example.de
starteroptionaler_variablenameDepartment:HR

or with start_ :

start_:MHI
start(Expression:user(MHI)
start_Firstname:Markus
start_Lastname:Hirscher
start_Email:Markus.Hirscher@example.de
start_Department:HR

Action Class

```
com.dooris.bpm.actionhandler.StartToProcessVariableActionHandler
```

Event Type

any

Action Name

any

Mandatory Fields

Prefix – if empty the standard starter is used as a prefix

Parameter

not necessary


Example

Symboleigenschaften - Aktivität


Symbol
BPMN-Anleitung
Modellierung
Eingaben
Ressourcen
Aufgabe
Ausgaben
Attribute
Letzte Simulation
Sonstige
Allgemein
Verknüpfungen
Benutzerdefinierte Daten
Risiken
Messgrößen
RACI
Automatisierung
Enterprise

Solldauer:

Aufgabenliste:

Aufgabenname	Rollenzuweisung
 Edit Event	
Ereignistyp:	Node Leave
Aktionsname:	StarterToProcessVariableActionHandler
Aktionsklasse:	onhandler.StartToProcessVariableActionHandler
Mandatory Fields:	optionaler_variablenname
Parameter:	

OK Abbrechen Übernehmen Hilfe



From:
<https://wiki.tim-solutions.de/> - **TIM Wiki / NEW TIM 6 Documentation**

Permanent link:
<https://wiki.tim-solutions.de/doku.php?id=en:software:tim:actionhandler:starttoprocessvariableactionhandler&rev=1453302998>

Last update: **2021/07/01 09:54**

