

Basics

The basic settings of the LDAP-connection can be adapted in tim-ldap.properties. In order to bring the make the connection compatible with the customer-needs, the file must be edited in a simple text editor.

Please contact the administrator to learn the LDAP-attributes or find more information at <http://www.selfadsi.de/>.

The ldap.properties

ldap.properties

```
#Here, the BaseDN is given, onto which the TIM builds the connection.  
This "index" is not changeable  
basedn=DC=tim,DC=local  
#The host name or the IP of the LDAP server  
host=salvator  
#Denotes the port of the LDAP server  
port=389  
#Denotes the use, with which the connection should be made. This  
requires only reading rights in LDAP  
username=ldapsync  
#The appropriate user password  
password=geheimgeheim  
#Here, the type of authorization may be denoted  
authentication=simple  
#The number of milliseconds elapsed until the connection should be  
broken  
timeout=60000  
#### Entries for the LDAP-Sync ####  
# === Group entries ===  
#Here the user may define the appearance of the groups that TIM works  
through in the LSAP sync. Example: (member=TIM-*) searches for all  
groups beginning with "TIM-"  
group.search=(member=*)  
#Denotes which attribute of the acticedirectory group should be used  
for the group name  
group.name=cn  
#This should remain "member" because this attribute is interpreted as  
the user in TIM  
group.member=member  
  
# === User-Entries ===  
#Denotes which class of objects (contacts, global groups, etc.) should  
be searched for by TIM in LDAP. Generally remains as "user"  
user.search=(objectClass=user)
```

```
#Here the LDAP attribute, which is to be used for the E-mail address,  
may be selected  
user.mail=mail  
#Here the LDAP attribute, which is to be used for the first name, may  
be selected  
user.firstname=givenName  
#Here the LDAP attribute, which is to be used for the surname, may be  
selected  
user.lastname=sn  
#Here the LDAP attribute, which is to be used for the user name, may be  
selected  
user.name=samaccountname  
#Here the LDAP attribute, which is to be used for the manager, may be  
selected  
user.supervisor=manager  
#OPTIONAL: Here the LDAP attribute, which is to be used for the  
password, may be selected  
#user.password=cn  
  
# ===Technical entries ===  
#Must be set, may NOT be changed!  
contextfactory=com.sun.jndi.ldap.LdapCtxFactory
```

From:

<https://wiki.tim-solutions.de/> - **TIM Wiki** / [NEW TIM 6 Documentation](#)

Permanent link:

<https://wiki.tim-solutions.de/doku.php?id=en:software:tim:ldap:tim-ldap.properties>

Last update: **2021/07/01 09:52**

